





In Outlook Express, from the **Tools** menu, select **Accounts...**




A box will appear. Click **Add** and select **Mail**.




Enter your name as you want it to appear on your emails and click **Next**.




Put in your email address, which consists of a user you set up in webmail and **@united.net**, and then click **Next**.



Set the server type as **POP3**. For incoming mail, enter **mail.united.net**. For outgoing mail, enter **smtp.united.net**. Click on **Next**.




Enter your email address for the **Account Name**. Enter the password you set for this account. **Note:** Do NOT check the box "Log on using Secure Password Authentication".



The screenshot shows the 'Internet Mail Logon' window from the Internet Connection Wizard. It prompts the user to enter their account name and password. The account name field contains 'user@yourdomainname.com' and the password field contains masked characters. The 'Remember password' checkbox is checked, and the 'Log on using Secure Password Authentication (SPA)' checkbox is unchecked. Navigation buttons for '< Back', 'Next >', and 'Cancel' are at the bottom.

Field	Value
Account name:	user@yourdomainname.com
Password:	XXXXXXXXXX

Click **Next** and then click **Finish**. After you click **Finish**, you should see the following window. If not, go to the **Tools** menu, and click on **Accounts**. After clicking **Accounts** the window will appear. In this window, click on your domain until it is highlighted, then click on **Properties**.



The screenshot shows the 'Internet Accounts' window with the 'Mail' tab selected. A table lists the accounts, and a set of control buttons is on the right.


Account	Type	Connection
mail.yourdomainname.com	mail	Any Available

Buttons: Add, Remove, Properties, Set as Default, Import..., Export..., Set Order..., Close

When the next screen appears, click on the **Servers** tab.

Under Outgoing Mail Server, check the box next to **My server requires authentication**.

Click **Okay**. **Note: You MUST do this step so you can send mail from your domain.**



The screenshot shows a dialog box titled "mail.yourdomain.xyz Properties" with a "Servers" tab selected. The dialog is divided into several sections:

- Server Information:** "My incoming mail server is a  server."
- Incoming mail (POP3):**
- Outgoing mail (SMTP):**
- Incoming Mail Server:**
  - Account name:
  - Password:
  - Remember password
  - Log on using Secure Password Authentication
- Outgoing Mail Server:**
  - My server requires authentication
  -

At the bottom of the dialog are three buttons: , , and .

Now, you're ready to send and receive mail. To set up multiple accounts, follow these steps again.